

# Plugin BigBlueButton

Use this [wiki plugin](#), introduced in [Tiki5](#), to invoke a [BigBlueButton](#) in a page.

## Parameters

Hold a video/audio/chat/presentation session using the BigBlueButton web conferencing system.

Introduced in Tiki 5. Required parameters are in **bold**.

[Go to the source code](#)

Preferences required: `wikiplugin_bigbluebutton`, `bigbluebutton_feature`

Parameters	Accepted Values	Description	Default	Since
<b>name</b>	text	MeetingID for BigBlueButton. This is a 5 digit number, starting with a 7. Ex.: 77777 or 71111.		5.0
showattendeess	alpha	Enable or Disable the display of attendees list.	y	
showrecording	alpha	Enable or Disable the display of video recordings.	y	
prefix	text	Unregistered users will get this token prepended to their name.		5.0
number	text	The phone-in support number to join from traditional phones.		5.0
logout	url	URL to which the user will be redirected after logging out of BigBlueButton.		5.0
voicebridge	digits	Code to enter for phone attendees to join the room. Typically, the same 5 digits of the MeetingID.		5.0
welcome	text	A message to be provided when someone enters the room.		5.0
recording	0 1	The recording starts when the first person enters the room, and ends when the last person leaves. After a period of processing (which depends on the length of the meeting), the recording will be added to the list of all recordings for this room. Requires BBB >= 0.8.	0	5.0

## Example

```
{bigbluebutton name="Room-Number" prefix="Guest: " voicebridge="Room-Number" logout="URL-of-the-logout-page" recording="1"}
```

You can see an example at [Live](#). Below is a screenshot:



# The main meeting room

Permissions

Join

No attendees at this time.



## BigBlueButton



Allows to join a BigBlueButton meeting.

<b>Meeting</b>	<input type="text" value="The main meeting room"/> MeetingID provided by BigBlueButton.
Anonymous prefix	<input type="text" value="Guest:"/> Unregistered users will get this token prepended to their name.
Welcome Message	<input type="text" value="Welcome to live.tikiwiki"/> A message to be provided when someone enters the room.
Dial Number	<input type="text" value="+1-999-999-9999"/> The phone-in support number to join from traditional phones.
Logout URL	<input type="text" value="http://tikiwiki.org/Live_"/> URL to which the user will be redirected when logging out from BigBlueButton.
Maximum Participants	<input type="text"/> Limit to the amount of simultaneous participants in the room. Support for this parameter depends on the BigBlueButton server.

Submit

Close

## Related pages

- [BigBlueButton](#)
- [Live](#)