

# Using Copyright Management

Use the Copyright feature to automatically include a copyright statement on specific pages, link to a full license page, and add the copyright information when printing.


1. Enable and configure the feature on the Copyright Admin page.

2. If enabled for **Wiki** pages:

- Tiki will add the following statement at the bottom of each page, with a link to your **License Page**:

The content on this page is licensed under the terms of the Copyright License Page

- When editing wiki pages, the following Copyright fields appear:



The screenshot shows a web form for editing a page's properties. At the top, there are tabs for 'Edit page' and 'Properties', and a 'No Tabs' button. The form is divided into two main sections: 'Copyright' and 'License'. The 'Copyright' section contains three input fields: 'Title:', 'Year:', and 'Authors:'. The 'License' section contains a dropdown menu labeled 'Copyright License Page'. Below the dropdown, there is an 'Important:' notice with a red exclamation mark icon, titled 'Copyright Submission Notice'. At the bottom left of the form, there is a link for 'Admin wiki preferences' with a key icon.

This allows users submitting content to attach a copyright notice to the page. The user enters the title of work being copyright (which may or may not be different to the page title), the year of copyright and the author(s) associated with the content.

Normal users can only add copyright notices to a page, and only administrators can delete or modify submitted ones. Copyright notices can then be recalled using the

## Copyright Notice Plugin.

- When printing a page, Tiki will automatically include the full **License Page**.

3. If enabled for **Articles**:

4. If enabled for **Blogs**:

5. If enabled for **FAQs**:

# Editing Copyright Notices

The ©MS uses the permission tiki\_p\_edit\_copyrights which allows users to access the copyrights edit page. To access the copyrights edit page for a particular page, go to the license page for that page and click on the link at the bottom of the page:



Created by: last modification: Tuesday 17 of , 2003 [16:48:51 BDT] by [Ricardo](#)  
To edit the copyright notices [click here](#).

If you have permissions this will take you to the copyright edits page where you can edit the copyright notices for that page:



Copyrights: [Home Page](#)

Title:	<input type="text" value="Netbook of Planes"/>	<input type="button" value="edit"/>
Year:	<input type="text" value="2003"/>	<a href="#">x up down</a>
Authors:	<input type="text" value="Ricardo Gladwell, Gary Lubben, Steve Dupp"/>	
Title:	<input type="text"/>	<input type="button" value="add"/>
Year:	<input type="text"/>	
Authors:	<input type="text"/>	

This page allows administrators to alter the order of copyright notices, edit their data or add new copyright notices. To edit a copyright notice simply alter the information in the text boxes and click the 'edit' button on the right-hand side.

To delete a copyright notice click on the 'x' on the right-hand side.

To move a copyright notice's order click on 'up' or 'down' on the right-hand side.

To add a new copyright notice simply fill in the information in the empty text boxes at the bottom of this page, as you would adding a copyright notice in the wiki edit page above, and click the 'add' button.

- [PluginCopyright](#)
- [Copyright Administration](#)

---

Useful Links

- [Creative Commons](#)  
<http://creativecommons.org/>
- [GNU/FDL](#)  
<http://www.fsf.org/copyleft/fdl.html>
- [Open Game License](#)  
<http://www.opengamingfoundation.org/ogl.html>
- [Open Publication License](#)  
<http://opencontent.org/openpub/>

## To be refactored

[+]

The Copyright Management System (©MS) allows you to specify a content license under which all wiki pages are published when submitted. When this feature is activated by an administrator, new form elements appear on the Wik

Edit Page :

2nd Round: The strength and location of each case 76

Comment:

Copyright: Title:

Year:

Authors:

Allow HTML:

Format:

This allows users submitting content to attach a copyright notice to the page. The user enters the title of work being copyrighted (which may or may not be different to the page title), the year of copyright and the author(s) associated with the content.

Normal users can only add copyright notices to a page, and only administrators can delete or modify submitted ones. Copyright notices can then be recalled using the Copyright Notice Plugin. This is normally only done in the license page. To view the license for a particular page click on the license link at the bottom of the page, for example:

Created by: last modification: Tuesday 08 of , 2003 [17:53:45 BDT] by [Ricardo](#)  
The content on this page is licensed under the terms of the [Open Game License](#).

This will take you to the license (in this case the OpenGameLicense) for that page. Depending on how the administrator has set-up the license you may also be able to peruse all the copyright pages for that page as well. Similarly, clicking on the PrintIcon will now take you to a full print-out of your page content *and* the license under which it is published.