

## Plugin BigBlueButton

Use this [wiki plugin](#), introduced in [Tiki5](#), to invoke a [BigBlueButton](#) in a page.

### Parameters

Introduced in Tiki 5. Required parameters are in **boxed**.

[Go to the source code](#)

Preferences required: `wikiplugin_bigbluebutton`, `bigbluebutton_feature`

Parameters	Accepted Values	Description	Default	Since
<code>name</code>	text	MeetingID for BigBlueButton. This is a 5 digit number, starting with a 7. Ex.: <code>77777</code> or <code>71111</code> .		5.0
<code>showattendees</code>	alpha	Enable or Disable the display of attendees list.	y	
<code>showrecording</code>	alpha	Enable or Disable the display of video recordings.	y	
<code>prefix</code>	text	Unregistered users will get this token prepended to their name.		5.0
<code>number</code>	text	The phone-in support number to join from traditional phones.		5.0
<code>logout</code>	url	URL to which the user will be redirected after logging out of BigBlueButton.		5.0
<code>voicebridge</code>	digits	Code to enter for phone attendees to join the room. Typically, the same 5 digits of the MeetingID.		5.0
<code>welcome</code>	text	A message to be provided when someone enters the room.		5.0
<code>recording</code>	0 1	The recording starts when the first person enters the room, and ends when the last person leaves. After a period of processing (which depends on the length of the meeting), the recording will be added to the list of all recordings for this room. Requires BBB >= 0.8.	0	5.0

### Example

```
{bigbluebutton name="Room-Number" prefix="Guest: " voicebridge="Room-Number" logout="URL-of-the-logout-page" recording="1"}
```

You can see an example at [Live](#). Below is a screenshot:



# The main meeting room

Permissions

Join

No attendees at this time.



## BigBlueButton



Allows to join a BigBlueButton meeting.

<b>Meeting</b>	<input type="text" value="The main meeting room"/> MeetingID provided by BigBlueButton.
Anonymous prefix	<input type="text" value="Guest:"/> Unregistered users will get this token prepended to their name.
Welcome Message	<input type="text" value="Welcome to live.tikiwiki"/> A message to be provided when someone enters the room.
Dial Number	<input type="text" value="+1-999-999-9999"/> The phone-in support number to join from traditional phones.
Logout URL	<input type="text" value="http://tikiwiki.org/Live_"/> URL to which the user will be redirected when logging out from BigBlueButton.
Maximum Participants	<input type="text"/> Limit to the amount of simultaneous participants in the room. Support for this parameter depends on the BigBlueButton server.

Submit

Close

## Related pages

- [BigBlueButton](#)
- [Live](#)