

Wiki General Preferences tab

Overview

Use this tab to set the primary wiki options.

To Access

From the [Administer Wiki](#) page, click the **General Preferences** tab.

Related Topics

- [Wiki](#)
- [Wiki Syntax](#)

Option

[Wiki](#)

Wiki homepage

Description

Pages and collaboratively authored documents with edit history.

The default home page of the wiki when no other page is specified. The page will be created if it does not already exist.

Default

Enabled

HomePage


Option

Wiki URL scheme

Prevent special characters in page names

Description

Alter the SEFURL pattern for page names.

 *Use the "View" action to regenerate your URLs after changing this setting.*

 Replace spaces with dashes | Replace spaces with underscores | URL Encode (Tiki Classic)

Some characters in a wiki page name may prevent the page from being easily accessible via the URL or wiki links. This option prevents the creation of page names with such characters.

Default

Replace spaces with dashes

Enabled

Option

Wiki link format

Description

Level of special characters acceptable in wiki links for page names. For example: [Page](#)

[é](#); [à](#); [î](#)

* *"Strict" includes only basic characters such as a-z and 0-9. A site that uses accented or special characters in page names should not use "strict".*

☰ Complete | Relaxed | Strict

Default

Complete

Option

Page name display stripper

Display page name as page title

Display the page name above the page area

Description

The character(s) to use as a delimiter in the page name. The portion of the name after the character(s) will not be displayed. If the page name display stripper conflicts with the namespace separator, the namespace is used and the page name display is not stripped.

Display the page name at the top of each page as page title. If not enabled, the page content should contain an h1 heading to function as the page title, or the page description can be used as the title.

Display the page name in small text at the top of each page (above the page's content).

Default

None

Disabled

Disabled

Option

Display the page name inside the page content

Add an option to hide the page title per wiki page

Anchor links on headings

Show the page description

Description

Display the page name inside the page content.

Enable the page title to not be displayed, on a per-page basis.

Cause a link icon to appear on hover over each heading, useful for sharing the URL to an exact location on a page.

☰ h1 only | h2 and above | h3 and above | h4 and above | h5 and above | h6 and above | none (disabled)

Display the wiki page description between the page title and the page content.

Default

Disabled

Enabled

h6 and above

Disabled

Option

Display input at top of Edit tab

Show the page ID

Show the page version

Wiki author list style

Description

More prominent location than on Properties tab

Each wiki page has a numeric ID and this can be displayed.

Display the page version information when viewing the page.

Change the list format that is used to display the authors of the page.

☰ Creator and Author | Business style | Collaborative style |
Page last modified on | none (disabled)

Default

Disabled

Disabled

Disabled

none (disabled)

Option

Specify wiki author list style per page

Encourage contribution to wiki pages by anonymous

Show/hide icon before headings

Description

Enable the style in which the author list is displayed to be modified on a per-page basis.

When a page is not editable because the user is anonymous, display the edit buttons anyway. The visitor will be prompted with a log-in screen and will be encouraged to register in order to be able to edit the page.

For use with the !!- or !!+ syntax. Activating this will display the show/hide icon at the left of the heading; otherwise, it displays below.

Default

Disabled

Disabled

Disabled

Option

Wiki page edit buttons location

Wiki navigation bar location

Description

Specify the location of the Save, Preview, and Cancel buttons on the wiki edit page.

☰ Top | Bottom | Both

When using the

Default

Bottom