### Deprecated and last code finally killed in Tiki15

Maps have been supported in Tiki since 2003 (which is why some call it a GeoCMS). There is geo-related info in various places (users, trackers, image galleries, articles, blog posts, etc.). This was originally done using MapServer, an active and powerful FLOSS mapping solution. However, it requires a dedicated server and more importantly, access to map data (which is not easy). MapServer in Tiki was not maintained since 2004. This likely was influenced by the fact, that Maps integration in Tiki over times moved to GoogleMaps (GMap) in favor to MapServer. Further on we moved from GMap to OpenLayers / OpenStreetMap, which is the base for Map integration in Tiki ever since.

#### Please visit the following pages, if you want to use Maps in Tiki: OpenLayers, Maps, PluginMaps

Please mind: This page stays here only for historic reasons and to guide to Tiki's OpenLayers page

Table of Contents

# Mapfile structure

# COMMENTS

Any text after a *#* is a comment. Use comments a lot to document your mapfile.

# **OBJECTS OR GROUPS**

mapfile is composed of several objects. Each object start by the keyword object and finishes by END. Inside an object there can b several objects with the object starting by its keyword and finishing by END. A mapfile starts by the keyword MAP and finishes by END Inside the mapfile there are objects like layers, each layer start by the keyword LAYER and finishes by END

MAP		
LAYER		
 END # end of layer		
LAYER		
END # end of layer END # end of map		

Do not try to figure how many END you need to put in the mapfile but use indentation to clearly identify each object with its keyword, text and END keyword. All objects are nested and with proper indentation, they are clearly visible. Indentation is not required but facilitates understanding a mapfile. Adequate comments help a lot too.

## A WORD ON COLORS

The keyword COLOR, OUTLINECOLOR,.. specify the color in the RGB color space. The first value is the red intensity from 0 (no red) to 255, the second value is the green intensity from 0 (no green) to 255 and the last value is the blue intensity from 0 (no blue) to 255. A COLOR 0 0 0 indicates black while COLOR 255 255 255 indicates white. COLOR 0 255 0 would be pure green. The 3 values are compulsory and must be numbers. To select some correct values, use a color selector like the one inside MS-Paint in accessories. You select the color and the RGB values are indicated.

# Mapfile header

The mapfile header is composed of several objects for the representation of the maps on the screen, you have the map itself, the web object to define how the web image is created, the reference or overview, the scalebar, the legend and if the map should be queryable. It is better to use pre-canned header and modify little parameters to conform to a specific map. This is the standard header for a map object

#

#
# Start of map file
+
МАР
NAME "Efate"
STATUS ON
SIZE 400 400
EXTENT 196900 8027100 245000 8073000
UNITS METERS
TRANSPARENT OFF
SHAPEPATH "/var/www/html/map/"
IMAGETYPE png24
FONTSET "fonts/fontset.txt"
OUTPUTFORMAT
NAME png24
DRIVER "GD/PNG"
MIMETYPE "image/png"
IMAGEMODE RGB
EXTENSION "png"
END
#
# Start of web interface definition
#
WEB
TEMPLATE /var/www/html/map/map.html
IMAGEPATH /var/www/html/map/images/
IMAGEURL /map/images/
LOG /var/www/html/map/maplog
END
#
# Start of reference map
# Start of reference map
# REFERENCE
IMAGE /var/www/html/map/data/efate.png
EXTENT 196900 8027100 245000 8073000
STATUS ON
COLOR -1 -1 -1
OUTLINECOLOR 255 0 0
SIZE 95 95
END

```
#
# Start of legend
#
LEGEND
 KEYSIZE 18 12
 LABEL
   TYPE BITMAP
   SIZE MEDIUM
   COLOR 0 0 89
 END
 STATUS ON
END
#
# Start of scalebar
#
SCALEBAR
 IMAGECOLOR 255 255 255
 LABEL
   COLOR 0 0 0
   SIZE SMALL
 END
 SIZE 350 5
 COLOR 255 255 255
 BACKGROUNDCOLOR 0 0 0
 OUTLINECOLOR 0 0 0
 UNITS kilometers
 INTERVALS 5
 STATUS ON
END
#
# Start of query definitions
#
OUERYMAP
 STATUS ON
 STYLE HILITE
END
```

Tip: A quick way to start a mapfile is to take the above and just add a END at the end of it. Point to a real image in the REFERENCE section and change all the paths to reflect your own installation. You will have then a working mapfile with no layers. You can then add a GRID to it and start to make modification to suit what you really want to achieve.

It is important here to have the following paths set correctly in regards to where you installed the mapfiles:

- SHAPEPATH
- IMAGEPATH

- IMAGEURL
- IMAGE

See their definition later in the text

### MAP OBJECT

MAP NAME "Efate" #name of the map file STATUS ON # is this map on by default SIZE 400 400 # size in pixel of the image map EXTENT 196900 8027100 245000 8073000 # geographic extents of the map UNITS METERS # units for the geographic extents TRANSPARENT OFF # the background is not transparent SHAPEPATH "/var/www/html/map/" # where the shapefiles are stored on the # server also used for directory reference IMAGETYPE png24 # type of image output, here PNG format in 24bits color FONTSET "fonts/fontset.txt" # file containing the locations of fonts

### WEB

This group defines where to store information on the server and how to provide it to the web browser

WEB

- TEMPLATE /var/www/html/map/map.html
- # location of the template for results
- # the line needs to be here, but it is
- # not used (no file at this location)
  IMAGEPATH /var/www/html/map/images/
- # location where to store maps images
  IMAGEURL /map/images/
- # web path for the maps images LOG /var/www/html/map/maplog

#### METADATA

#### VIEW

View allows you to create views so you can quckly move to the geographic location, for instance moving from one country to another one.

#### WEB

#### METADATA

VIEW1 "American Samoa,181.496593149,-20.0990853659,199.331777248,-8.22408536586" VIEW2 "Australia,97.5030380511,-48.984521576,168.843774449,-1.48452157598" VIEW3 "Cook Islands,180.098325105,-27.4401969982,215.768693304,-3.69019699813"

END

Each view needs to be numbered in sequential order. Each field is separated by commas, the first field is the name of the view, the following fields are minx,miny,maxx,maxy of the view.

Cf. Maps MapView for a detailed description.

### REFERENCE

This group defines how the overview should be displayed. You use an image representing the area of interest and you specify the coordinates of the location of the edge of the image. The system will draw on the image a rectangle based on the current view, indicatin the boundaries of such view.

REFERENCE
IMAGE /var/www/html/map/data/efate.png
<pre># location of the image</pre>
EXTENT 196900 8027100 245000 8073000
<pre># extent of the image</pre>
STATUS ON
# the overview is on by default
COLOR -1 -1 -1
<pre># transparent background</pre>
OUTLINECOLOR 255 0 0
# the color of the outline
STZF 95 95
# the size of the image in pixels
END

The tip to create an image for overview, is to not worry about the image at the begining. Any image will do. When the layers are implemented in the mapfile and the main view sounds pretty enough, then select a default view, click *Redraw* if neccessary to get the minx, maxx, miny, maxy parameters in the URL, (if necessary adjust them manualy). Save the current map as an image onto your local machine, use an image editing software to resize the image to the size you want to use in the overview (here 95x95 pixel). Upload the image using the *maps->layer manager* and update the IMAGE link in the REFERENCE group to point to this new image. Finish by entering the correct EXTENTS that corresponds to the minx, miny, maxx, maxy of the map you used to create the overview.

### LEGEND

The legend is linked to each LAYER by the way each object type is represented (POINT, LINE, POLYGON,...) and its COLOR and OUTLINECOLOR and by the NAME used in the CLASS group. It is important to have a meaningful NAME for each CLASS group in every LAYER group. The NAME of the CLASS can be different from the NAME of the layer as a LAYER can have several CLASSes.

LEGEND KEYSIZE 18 12 # the size of the object representing the # geographical object LABEL TYPE BITMAP # Font type for the legend name of each # geographical object SIZE MEDIUM # font size COLOR 0 0 89 # font color

### SCALEBAR

It is interesting to display a scalebar to get information on distances.

SCALEBAR IMAGECOLOR 255 255 255		
<pre># background color of the image placeholder</pre>		
LABEL		
COLOR 0 0		
<pre># color of the labels indicating the distance SIZE SMALL</pre>		
# size of the labels		
END		
SIZE 350 5		
<pre># sixe in pixels of the scalebar</pre>		
COLOR 255 255 255		
<pre># color used in the scalebar</pre>		
BACKGROUNDCOLOR 0 0 0		
<pre># background color of the drawn scalebar</pre>		
OUTLINECOLOR 0 0 0		
<pre># outline color of the salebar</pre>		
UNITS kilometers		
# units to be used		
INTERVALS 5		
# How many intervals in total in the		
# scalebar		
STATUS ON		
# the scalebar is on by default END		

# QUERY

his group secify that the map will be queryable and how the selected objects should be represented. Include this group even if yo don't have a LAYER that can be queryable. It will certainly come later.

QUERYMAP STATUS ON # the map is queryable by default STYLE HILITE

# Layers

# VECTOR LAYER

et's start by a very simple layer that we will add more features to it. A layer start by the keyword LAYER and finishes by END. It ca include CLASS groups, METATADATA groups. For a vector layer the CLASS is compulsory.

### LAYER TYPE

rhe two main types of GIS vector are ESRI shapefiles of Mapinfo TAB files. ESRI shapefiles are natively supported while the Mapinfo filesare supported via the OGR library.

All locations of files must be indicated in relative reference to the path indicated by the keyword SHAPEPATH in the MAP group. If you have a file in "/var/www/html/map/data/mylayer.shp and SHAPEPATH indicates "/var/www/html/map/" then your file location must be "data/mylayer.shp". Using this convention allows you to easily locate files when you upload them using Maps->Layer Management.

ile names are case sensitives and spaces in file names must be absoutely avoided. The extensions used for files in layer must stay ith the same case sensitivity. A shapefile is usually made of a shp, idx, dbf files while a Mapinfo layer is made of TAB, ID, MAP, DA (and sometimes IND) files.

SHAPEFILE

LAYER NAME "My Layer" TYPE LINE STATUS ON DATA "data/myshapefile.shp" CLASS COLOR 255 0 0 NAME "My layer legend" END # end of class END # end of layer In this example we see that the file is located in "data/", it is made of LINE objects that will be displayed with the COLOR red. The layer should be drawn on the map by default (STATUS ON), and it will be indicate as "My Layer" in the layer manager on the map, while being indicated as "My layer legend" in the LEGEND.

#### MAPINFO TAB

The difference with a shapefile is the use of the OGR library to read the Mapinfo files. The keyword CONNECTIONTYPE OGR must be used and the location of the file is given by the keyword CONNECTION instead of DATA. All the rest stay the same.

LAYER NAME "My Layer" TYPE LINE STATUS ON CONNECTIONTYPE OGR CONNECTION "data/mymapinfofile.TAB" CLASS COLOR 255 0 0 NAME "My layer legend" END # end of class END # end of layer

### QUERY

To make the layer queryable add anywehere inside the LAYER object the following lines:

TEMPLATE "query.html" TOLERANCE 3 TOLERANCEUNITS PIXELS

The first parameters is necessary but does not need to pint to a real file. It is only used outsied tikimaps. The second parameters specify the pointing TOLERANCE in TOLERANCEUNITS, here 3 pixels. If you click on the map all the objects from this layer which are at less than 3 pixels from the click on the image will be selected.

The map is then redraw and at the bottom of the page will be the information related from the object.

lote: if you create a GIS layer which fields contain HTML tags, like for IMG or A (anchor/link), they will be rendered accordingly. Thi

allows you to create a layer pointing to images stored on Tiki.

#### LABELS

ou can use querying to know which fields a GIS layer contains. From these fields you can select on to be used a object labels in th map. For instance you have a GIS layer which contains country names. The name of the country is in the field "NAME". You will use LABELITEM "NAME" to tell the mapserver which field to use for labels.

Inside the CLASS object, you would specify how you want the labels to be rendered. For instance in our example the layer would look like this:

LAYER		
NAME "Country Names"		
TYPE POINT		
STATUS ON		
METADATA		
DOWNLOAD "T"		
END		
LABELITEM "NAME"		
LABELCACHE ON		
CONNECTIONTYPE OGR		
CONNECTION "data/Country.TAB"		
CLASS		
SYMBOL 0		
COLOR 0 0 0		
NAME "Country Names"		
LABEL		
COLOR 0 0 0		
FONT arial		
TYPE TRUETYPE		
POSITION CC		
PARTIALS TRUE		
SIZE 7		
BUFFER 1		
OUTLINECOLOR 255 255 255		
END		
END		
END	 	 

In this example LABEL is black (COLOR 0 0 0) using the arial FONT which is a TRUETYPE font. The POSITION of the label is enter/Center in regard to the POINT object. If an object is not fully on the map, the LABEL is still drawn (PARTIAL TRUE). The SIZE of he label is 7 points. There are no labels closer than 1 pixels from each others (BUFFER 1). For this last parameter to work, you nee to enable the LABELCACHE. Finally the label is surrounded by a white outline (OUTLINECOLOR 255 255 255).

#### THEMATIC MAPPING

Each layer contans one or more CLASS. The CLASS defines how each object should be drawn on the screen. by using CLASSITEM, ou can use one field to separate objects in classes. For instance all the bathymetric lines which depth is between -100m and -500r elong to one class while each bathymetric lines which depth is between -500m and -1000m belong to another class. The separatio into CLASS is made using an EXPRESSION in each CLASS. The EXPRESSION uses simple logic based on the field in CLASSITEM. For instance in the example below we use the field "value" which contain the water depth of the LINE object to display this line bject in various colors depending of the depth. If the EXPRESSION is true then the parameters in the CLASS apply. A CLASS withou an EXPRESSION is a default CLASS for all the objects which have not been classified otherwise.

AYER	
NAME "Bathymetry 20m"	
TYPE LINE	
STATUS OFF	
METADATA	
WIKI "FijiBathymetry"	
END	
TEMPLATE "query.html"	
TOLERANCE 3	
TOLERANCEUNITS PIXELS	
LABELITEM "Value"	
CLASSITEM "Value"	
LABELCACHE ON	
CONNECTIONTYPE OGR	
CONNECTION "data/fiji/viti_bathy_contour.TAB"	
CLASS	
SYMBOL 0	
COLOR 0 200 255	
NAME "Bathymetry 2.5m >-50m"	
expression ([Value]>-50)	
LABEL	
ANGLE AUTO	
COLOR 0 0 0	
FONT arial	
TYPE TRUETYPE	
POSITION cc	
PARTIALS FALSE	
BUFFER 5	
SIZE 6	
OUTLINECOLOR 200 200	
END	
END	
CLASS	
SYMBOL 0	
COLOR 0 100 255	
NAME "Bathymetry 20m >-500m"	
expression ([Value]<-50 AND [Value]>=-500)	
LABEL	
ANGLE AUTO	
FONT arial	
COLOR 0 0	
	-

	TYPE TRUETYPE
	POSITION cc
	PARTIALS FALSE
	BUFFER 5
	SIZE 6
	OUTLINECOLOR 200 200 200
EN	D
END	
END	

### METADATA

Inside a LAYER group you can have a METADATA group. Some of this metadata is used for special purposes inside tikiwiki. There is only one METADATA group inside a LAYER group.

WIKI

Using WIKI creates a link from the layer name to a wiki page. Use the wiki page to indicate some information on the layer:

- custodian
- ownership
- date of creation
- accuracy
- history

•

- datum/projection
- interesting layer features

METADATA WIKI "MyLayerPage" END

#### DOWNLOAD

If DOWNLOAD is set to "T" then the files that forms the layer can be downloaded by a registered user.

METADATA DOWNLOAD "T" END

The system selects all the files with the same base name as defined in the LAYER DATA or CONNECTION clause but with different extension. However if one of these files has the extension NDL, the download is disabled. This allows to upload GIS data that can only be viewable.

# RASTER LAYER

The easiest way to handle raster layers is to use Geotiff images which contain projection information. However making geotiff images may need advanced remote sensing software. The other way is to use an additional file which contains information about the coordinates of the pixels in the image file.

When several images are used instead of using a layer for each image they can be tiled. A shapefile is created with a rectangel for each image which helps the system to find the right image for the right location.

### GEOTIFF

sing a geotiff image in a layer is simple, the TYPE RASTER is used with DATA pointing to the tiff file. the keyword OFFSITE is used t define which color in the tiff image should be used for transparency. This is useful when tiling or overlapping several images.

LAYER NAME "DTM 50m" TYPE RASTER STATUS OFF DATA "data/fiji/VLevudtm.tif" OFFSITE 0 0 0 END

#### **IMAGE TILES**

Images tiles are created using utility tools from the mapserver software. The utility is called gdaltindex and parses mainly geotiff images to get their boundaries and create a shapefile containing an outline for each of the images. Under Maps->Layer Management, at the bottom of the page a utility is available to generate the shapefile. Basically upload the images to the right lirectory. The images should have the same name prefix. Then reference all these images with a wildcaard and name the shapefile to be created. For instance you can upload coralcoastsigatoka.tif, coralcoastmomi.tif, coralcoastnavua.tif and reference them as coralcoast\*.tif and create the shapefile img\_index.shp

LAYER NAME "Coral Coast 4m IKONOS" TYPE RASTER METADATA WIKI "FijiImagery" END STATUS ON TILEINDEX "data/fiji/img\_index.shp" TILEITEM "Location" OFFSITE 0 0 0 END

# **GRID LAYER**

grid layer allows you to draw a grid in the local cordinates on your map. It is useful to find location of objects on the map. For bes effect the grid must be the last layer in the mapfile to be drawn the last.

LAYER			
NAME "Grid"			
TYPE LINE			
STATUS OFF			
CLASS			
COLOR 0 0 0			
LABEL			
FONT arial # must be in you	FONTSET		
TYPE TRUETYPE			
SIZE 8			
COLOR 0 0 0			
OUTLINECOLOR 255 255 255			
END			
END			
GRID			
MINARCS 2			
MAXARCS 6			